

System for Convection Analysis and Nowcasting (SCAN)

Guide for Users

version OB2

August 28, 2003

NWS - MDL

Table of Contents

Table of Contents	2
Introduction	4
What’s New in OB2	6
Requesting the SCAN Suite	6
The D2D	5
The SCAN Storm Cell Table Constituents:	5
The Menu/Information Bar	5
The Attribute Title Row	8
The Table Body	9
The Inspection Row	9
Trend Window	12
Attribute Color Threshold (ACT) Window	13
Rate-of-change Alarm Threshold Window	14
Alarm Information Window	14
Edit/Create Trend Set Window	15
The SCAN Mesocyclone Table Constituents:	15
The Menu/Information Bar	15
The Table Body	18
The Inspection Row	19
The SCAN TVS Table Constituents:	19
The Menu/Information Bar	19
The Attribute Title Row	21
The Table Body	22
The Inspection Row	23
SCAN CWA Threat Index (SCTI)	23
SCAN “New” Alarms	24
SCAN QPF	25
Data Monitoring System (DMS)	25

Figures	28
Help	33
Glossary	33
Appendix A SCAN Storm Cell Table Attributes	34
Appendix B SCAN Mesocyclone Table Attributes	37
Appendix C SCAN TVS Table Attributes	38

Introduction

The System for Convection Analysis and Nowcasting (SCAN) is an integrated suite of multi-sensor applications which detects, analyzes, and monitors convection and generates short-term probabilistic forecast and warning guidance for severe weather automatically within AWIPS. SCAN will provide forecasters with accurate, timely, and consistent severe weather guidance and supplement forecaster event monitoring with multi-sensor, automated event monitoring. The intended benefits are:

- ⚙ Longer lead times on warned events
- ⚙ Fewer missed events
- ⚙ Increased forecaster situational awareness
- ⚙ Reduced forecaster fatigue during warning situations

What's New in OB2

- ▶ The Storm Cell Table now has a toggle with which you can exclude the storm cells identified outside the CWA from alarm consideration and listing in the Cell Table.
- ▶ SCAN has a new “New Alarm” window which appears to the left of the screen (not over the main panel of the D-2D) and it does not take the mouse cursor focus.

Requesting the SCAN Suite

On the D2D, there is a menu entitled “SCAN”. Under the SCAN menu will be sections for each dedicated radar. Each of these radar sections has the available SCAN and FFMP (Flash Flood Monitoring and Prediction) products.

Selecting the SCAN Suite will load: the Storm Cell Identifications (white, yellow, and red), the Site Storm Threat, the SCAN Storm Track, and the Storm Cell Display, which is the cell table's link to the D2D. Also, the SCAN loading window will appear while the SCAN elements are loading. Figure 1 shows the SCAN Storm Cell Table.

The D2D

Once the SCAN Suite is loaded, on the D2D you will see identified storm cells, local sites, and storm tracks. The Storm Cell Table will appear in front of the D2D. The storm cell identification symbols are a circle, speed/direction arrow, and an alphanumeric identifier places outside the upper left part of the circle.

The SCAN Storm Cell Table Constituents:

See Figure 1.

The Menu/Information Bar

Contains the File, Configurations, Rank, and Attributes menus, as well as information regarding alarms, the currently utilized configuration file name, and the valid time of the SCAN Storm Cell Table. The Menu/Information bar also contains the option buttons for Link to Frame (to link the table time with the D2D display time), Vert (to render the table vertically), and Tips (to provide helpful tips about table functions). See Figure 5 for an example of the vertical table.

The File Menu

The File Menu options are for controlling the configuration files. The current configuration file is displayed on the menu button. This file indicates which configuration file (also known as the Cell Display Parameters file or CDP file) was last used in the cell table and that is being used by the D2D Storm Cell ID Display. The File Menu options are:

Retrieve Default CELL Configuration	Retrieves and uses the default configuration file.
Retrieve CELL Configuration . . .	Retrieves and uses a specified configuration file.
Save All Configurations	Saves the current configuration files for all three types (cell, mesocyclone, and TVS).
Save CELL Configuration	Saves only the cell configuration file.

Save CELL Configuration As . . .	Saves the cell configuration file to a new file, defined by the user.
----------------------------------	---

The Configurations Menu

The Configurations Menu choices are for setting up the D2D display, changing the alarm parameters, and controlling the Trend functions. The Configurations Menu options are:

D2D Display. . .	Produces the Storm Cell Identification Display (SCID) window (see Figure 2). The SCID window allows the user to control how the D2D displays the storm cell identifications.
Alarm Thresholds. . .	Produces the Rate-of-change Alarm Thresholds (RoCAT) window. The RoCAT window allows the user to define the rate-of-change limit for each applicable storm cell attribute. If the attribute's value changes more than this defined limit from one volume scan to the next, an alarm will be issued.
Trend Sets►	Produces selections that allow the user to choose which of the defined trend sets will be used as the active trend set as well as create and edit other trend sets. The active trend set is that which is accessible by the D2D and by the body of the cell table (see the "Table Body" section).
Alarm Time Setup. . .	Produces the 'New' Alarm Time Setup window. Along with rate-of-change alarms, SCAN will also issue a "New" alarm if an event (cell, mesocyclone, or TVS) has been identified after a quiet period of no identifications. This window allows the user to define that quiet period in minutes.
Box Colors. . .	Produces the Attribute Color Threshold (ACT) window. The ACT window allows the user to define value ranges of each applicable storm cell attribute. These value ranges are intended to reflect the degree of strength of the storm cell, from white (weak) to yellow (moderate) to red (strong). These colors will be used when rendering the data on the D2D, in the table body, and in the time trends. Note: The SCID window also provides this ability (see "D2D Display..." above).

The Rank Menu

Allows the user to choose the storm cell attribute by which the data in the table body will be sorted. The attribute that is currently being used for ranking is displayed on this button. Refer to Appendix A to see which attributes can be used for ranking.

The Attributes Menu

Allows the user to choose which of the available storm cell attributes will appear in the storm cell table. Refer to Appendix A for information about all available attributes.

☐ Link to Frame

Indicates whether the valid time in the SCAN Storm Cell Table will always match the time in the D2D frame. If this button is activated and the user changes the frame in the D2D, the cell table will update to match the data shown on the D2D. If this is off, the data in the cell table will represent the *most recent available inventory time*.

☐ Vert

Indicates whether or not the table is vertically rendered. If this button is activated, the table orientation will change from horizontal (default) to vertical. (See Figure 5).

☐ Tips

Indicates whether or not the Tips functionality is turned on. When this button is activated and the mouse cursor is focused over “clickable” widgets in the table, a pop-up text box will appear next to the cursor containing useful information on the available features of that particular widget.

Alarm Button

If a Rate-of-change Alarm Threshold is surpassed for an applicable attribute from one volume scan to the next, an alarm is issued. When an alarm is issued, a blinking alarm button will appear. The appropriate grid box in the table body will also blink and an audible alarm will

sound. Right-clicking on the Alarm button will toggle the audible alarm. Left-clicking on the Alarm button will produce the Alarm Information window (see Figure 1).

Valid Time

This displays the UTC time for which the data in the cell table is valid.

The Attribute Title Row

Shows what attributes are currently selected for viewing. These represent the attributes selected from the Attributes menu described above.

Ranking By Attribute

Left-clicking on applicable attribute titles will sort the table data according to that attribute. Refer to Appendix A to see for which attributes the table can be ranked.

Changing the Attribute Color Thresholds

Right-clicking on applicable attribute titles will bring up the Attribute Color Threshold (ACT) window, as described in the “Configurations Menu” section above. Refer to Appendix A to see which attributes can be multi-colored.

Launching the TVS and Mesocyclone Tables

Right-clicking on the ‘tvs’ or ‘meso’ attribute titles will produce the SCAN Tornado Vortex Signature (TVS) Table and the SCAN Mesocyclone (MESO) Table, respectively.

The Table Body

Displays the storm cell information, including such attributes as: alphanumeric identifier, location (azm/range, lat/lon, state/county), circulation, and various severe weather probabilities and physical storm characteristics. If no storm cells have been identified, the message “NO CELL DETECTIONS” will appear in place of the table. The values for the various storm cell attributes are displayed in the table body and color coded (when applicable) according to the attribute color thresholds defined in the ACT or SCID windows. Refer to Appendix A for a list of all storm cell attributes available through SCAN.

Producing a Time Trend

Left-clicking on any applicable grid box will produce a single time trend of a particular attribute of a particular identified storm cell. Refer to Appendix A to see for which attributes time trends are available. See Figure 1 for an example of a single time trend.

Producing a Trend Set

Right-clicking on a storm identifier in the ‘ident’ column will produce an ‘active’ trend set for that particular storm cell. The ‘active’ trend set can be defined by selecting the Trend Set option under the Configurations menu (see the section on trend sets in “SCAN Storm Cell Table Sub-GUIs in Detail” below).

Inspecting a Storm Cell

Left-clicking on an identifier in the ‘ident’ column will cause the D2D to zoom-and-recenter on that particular storm cell. This also fills the Inspection Row with data and highlights the identifier in the ‘ident’ column. The Inspection Row can be seen in Figure 1.

The Inspection Row

Duplicates the row in the table body for the storm cell that was last inspected (see the section on storm inspection under the “Table Body” topic for instructions on how to inspect a storm cell). This row emphasizes the data for the identified storm cell last inspected via the zoom-and-recenter method. The individual grid boxes in the Inspection Row have the same capabilities as the grid boxes in the table body, except left-clicking on the identifier box will zoom the D2D back out to the zoom level defined on the D2D menu bar. See Figure 1.

Producing a Time Trend

See information under the “Table Body” section above.

Producing a Trend Set

See information under the “Table Body” section above.

Zooming Back Out

Left-clicking on the identifier in the ‘ident’ column will cause the D2D to zoom back out.

SCAN Storm Cell Table Sub-GUIs in Detail

Storm Cell Identification Display (SCID) Window

Launched from the Configurations menu. The Storm Cell Identification Display (SCID) window allows the user to control the appearance of the storm cell identifiers on the D2D and define the zoom factor. See Figure 2.

The Zoom Factor: This number represents the magnitude of the zoom used when zooming and re-centering is done *from the table* (see the section on storm inspection in the “Table Body” section). Left-clicking the desired radio button will change the zoom factor. A larger number represents greater magnification. Either the “OK” or “Apply” button must be pressed for a change in Zoom Factor to take effect. Note: this Zoom Factor does **not** affect the D2D’s zooming abilities. Only the zoom-and-recenter functionality of the SCAN table when zooming and re-centering on a specific cell can be affected by this Zoom Factor.

Symbols: This portion of the window contains the available options for representing a cell identification on the D2D. These are not mutually exclusive choices. They can be chosen in any combination

Circles: are used to identify the location of a cell AND give a graphical indication of the strength of a chosen attribute of the cell. The available attributes can be viewed and selected by left-clicking on the menu button with the attribute name on it. This attribute’s column title button will have a dark green background in the Storm Cell table to indicate its status as the current Radius Interpolation variable. The Radius Range slider control allows the user to choose the size of the circles. The low slider bar value corresponds to the low slider bar value on the Radius Interpolation slider control. The high slider bar value corresponds to the high slider bar value on the Radius Interpolation slider control. Values in-between these low and high values will be interpolated and the circle size adjusted accordingly.

Arrows: are used to represent the speed and direction of a cell. The length of the arrow is proportional to the speed of the cell. If the Full Shaft option is on, the entire length of the arrow

represents the speed of the cell. If the Full Shaft option is off, only the portion of the arrow *outside* the circle (if the Circle identifier is being used) represents the speed of the cell. This is done to avoid the illusion of greater cell speed for cells with small circle identifiers compared to cells with large circle identifiers. If the Circle identifier is turned off, it is recommended that the Full Shaft option is turned on.

Cell Identifier Clutter Control:	In the event that there are enough identified cells to clutter the screen, the user can adjust the attribute color thresholds to eliminate some of the less significant cell identifications from the D2D display. By adjusting the slider control bars, the user can choose the attribute thresholds which will determine what color the cell identifiers will be on the D2D display and in the Table Body (white, yellow, and red). The particular attribute used for controlling clutter is chosen by left-clicking the menu button with an attribute name on it. The attribute's column title button will have bright green text to indicate its status as the current Clutter Control variable. Note: If the storm cells do not reach the lowest threshold for the Clutter Control Variable, the cell will be rendered as a small white 'x' on the D2D.
“OK”	Accept the changes made and close the window.
“Apply”	Accept the changes made.
“Cancel”	Discard changes and close the window.

Trend Window

See the “Table Body” section above for instructions to produce a time trend window. See Figures 1 and 3 for examples. Whether the trend is one of several or the only trend in the Trend window, each time trend graph will have the same appearance. The x-axis represents time, labeled with hhmm UTC time. The y-axis represents the attribute, with pre-defined labels. The name of the attribute and its units are above the y-axis labels. (Note: If the value of the attribute for any plot point exceeds the pre-defined maximum axis value, the y-axis will be automatically re-defined and the y-axis labels will be highlighted in pink.) The plot points will be colored according to the defined attribute color threshold values for the selected attribute.

Changing To a Different Storm Cell:	Left-clicking on the 2-digit alphanumeric identifier above the graph will bring up a menu of all selectable cells. Choosing a different cell will cause the trend window to render the new cell's trend information.
-------------------------------------	--

Changing To a Different Attribute:	Left-clicking on the attribute button above the graph will bring up a menu of all selectable attributes. Choosing a different attribute will cause the trend window to render the cell's trend information for that attribute.
"Close"	Left-clicking will close the trend window.

Attribute Color Threshold (ACT) Window

Launched from the Configurations menu or the Attribute Title Row. The user can edit the color-coded strength values for any of the storm cell attributes displayed in the Attribute Title Row.

"Attribute:"	The user can switch to a different storm cell attribute. The units of the attribute will also appear on this button.
"Upper:", "Mid:", "Lower:"	The strength thresholds, corresponding to the attribute values that meet or exceed these threshold values.
"OK"	The user accepts the changes just made and closes the window.
"Cancel"	The user can discard the changes just made.

New Alarm Time Setup Window


Launched from the Configurations menu. This window allows the user to set the time thresholds for determining when new SCAN alarms are issued. "New" SCAN alarms are issued with the occurrence of activity after a quiet period equal to this user-defined value.

"Cell:"	The user can enter the time period (in minutes) that represents the amount of quiet time needed (no cell activity) before which a 'new' alarm is issued with the onset of cell activity.
"Meso:"	The user can enter the time period (in minutes) that represents the amount of quiet time needed (no mesocyclone activity) before which a 'new' alarm is issued with the onset of mesocyclone activity.

“TVS:”	The user can enter the time period (in minutes) that represents the amount of quiet time needed (no TVS activity) before which a ‘new’ alarm is issued with the onset of TVS activity.
“OK”	The user accepts the alarm time thresholds.
“Cancel”	The user can discard the changes just made.

Rate-of-change Alarm Threshold Window

Launched from the Configurations menu. This window allows the user to set the thresholds for determining when SCAN rate-of-change alarms are issued.

“Attribute:”	The user can select any applicable storm cell attribute.
“Rate of Increase:”	The user can define the number of units the value of a storm cell’s attribute must increase from one volume scan to the next in order to trigger an alarm. The units are also displayed here. Note: the value of the attribute must increase at least <i>one unit more</i> than the value entered here in order for an alarm to be issued.
“OK”	The user accepts the alarm conditions.
“  Bell”	The user can toggle the audible alarm.

Alarm Information Window

Launched by left-clicking on the Alarm button. See Figure 1 for an example. The buttons in the window are labeled with the storm cell alphanumeric identifier and the storm cell attribute for which the alarm has been issued.

Investigating Alarms:	Left-clicking on an individual alarm button in the Alarm Information window will bring up a trend window for that cell and attribute that caused the alarm, cause the D2D display to zoom and re-center on that cell, and display the cell's table data in the Inspection Row. Once all alarms have been investigated, the Alarm Information window will close.
"Clear All Alarms"	Clear all active alarms without inspection.

Edit/Create Trend Set Window

Launched from the Configurations menu/Trend Sets selection. See Figure 3. The user can edit an existing trend set's defined attributes, create a new trend set, or delete an unwanted trend set by following the directions in this window. The Active Trend Set, which is the trend set created from the D2D (see below) and the table body (see the "Table Body" section above), can also be defined.

"Add Attribute"	Allows the user to add an attribute to an existing trend set.
"Remove Attribute"	Allows the user to remove an attribute from an existing trend set.
"Select Trend"	Allows the user to select a defined trend set he/she wishes to edit/delete.
"Remove Trend"	Allows the user to delete a defined trend set.
"OK"	The user accepts the changes just made and closes the window.
"Cancel"	The user can discard the changes just made and close the window.

The SCAN Mesocyclone Table Constituents:

The Menu/Information Bar

Contains the File, Configurations, Rank, and Attributes menus, as well as information regarding alarms, the currently utilized configuration file name, and the valid time of the SCAN

Mesocyclone Table. The Menu/Information bar also contains the option buttons for Vert (to render the table vertically) and Tips (to provide helpful tips about table functions).

The File Menu

The File Menu options are for controlling the configuration files. The current configuration file is displayed on the menu button. This file indicates which configuration file (also known as the Mesocyclone Display Parameters file or MDP file) was last used in the meso table. The File Menu options are:

Retrieve Default MESO Configuration	Retrieves and uses the default configuration file.
Retrieve MESO Configuration...	Retrieves and uses a specified configuration file.
Save MESO Configuration	Saves only the mesocyclone configuration file.
Save MESO Configuration As...	Saves the mesocyclone configuration file to a new file, defined by the user.
Close MESO Table	Closes the mesocyclone table until it is activated again from the SCAN Storm Cell Table.

The Configurations Menu

The Configurations Menu choices are for changing the alarm parameters and controlling the display of the Mesocyclone table. The Configurations Menu options are:

Alarm Time Setup. . .	Produces the Alarm Time Setup window. SCAN will issue a “New” alarm if an event (cell, mesocyclone, or TVS) has been identified after a quiet period of no identifications. This window allows the user to define that quiet period in minutes.
Box Colors. . .	Produces the Attribute Color Threshold (ACT) window. The ACT window allows the user to define value ranges of each applicable mesocyclone attribute. These value ranges are intended to reflect the degree of strength of the mesocyclone, from white (weak) to yellow (moderate) to red (strong). These colors will be used when rendering the data on the D2D, in the table body, and in the time trends.

The Rank Menu

Allows the user to choose the mesocyclone attribute by which the data in the table body will be sorted. The attribute that is currently being used for ranking will be displayed on this button. Refer to Appendix B to see which attributes can be used for ranking.

The Attributes Menu

Allows the user to choose which of the available mesocyclone attributes will appear in the mesocyclone table. Refer to Appendix B for information about all available attributes.

☐ Vert

Indicates whether or not the table is vertically rendered. If this button is activated, the table orientation will change from horizontal (default) to vertical.

☐ Tips

Indicates whether or not the Tips functionality is turned on. When this button is activated and the mouse cursor is focused over “clickable” widgets in the table, a pop-up box will appear next to the cursor containing useful information on the available features of that particular widget.

Valid Time

This displays the UTC time for which the data in the mesocyclone table is valid.

The Attribute Title Row

Shows (in black) what attributes are currently selected for viewing. These represent the attributes selected from the Attributes menu described above.

Ranking By Attribute

Left-clicking on applicable attribute titles will sort the table data according to that attribute. Refer to Appendix B to see for which attributes the mesocyclone table can be ranked.

Changing the Attribute Color Thresholds

Right-clicking on applicable attribute titles will bring up the Attribute Color Threshold (ACT) window, as described in the Configurations menu section above. Refer to Appendix B to see which attributes can be multi-colored in the mesocyclone table.

The Table Body

Displays the mesocyclone information, including such attributes as: storm cell ID, mesocyclone ID, location (azm/range, lat/lon, state/county), and various physical characteristics of the mesocyclone. If no mesocyclones have been identified, the message “NO MESO DETECTIONS” will appear in place of the table. The values for the various mesocyclone attributes are displayed in the table body. Refer to Appendix B for a list of all mesocyclone attributes available through SCAN.

Inspecting a Mesocyclone

Left-clicking on an identifier in the ‘ident’ column will cause the D2D to zoom-and-recenter on that particular mesocyclone. This also fills the Inspection Row with data and highlights the identifier in the ‘ident’ column.

The Inspection Row

Duplicates the row in the table body for the mesocyclone that was last inspected (see the “Table Body” section above for instructions on how to inspect a mesocyclone). This row emphasizes the data for the identified mesocyclone last inspected via the zoom-and-recenter method. The individual grid boxes in the Inspection Row have the same capabilities as the grid boxes in the table body, except left-clicking on the identifier box will zoom the D2D back out to the zoom level defined on the D2D menu bar.

Zooming Back Out

Left-clicking on the identifier in the ‘ident’ column will cause the D2D to zoom back out.

SCAN Mesocyclone Table Sub-GUIs in Detail

New Alarm Time Setup Window

Same as for the cell table (see above).

Attribute Color Threshold (ACT) Window

Same as for the cell table (see above).

The SCAN TVS Table Constituents:

The Menu/Information Bar

Contains the File, Configurations, Rank, and Attributes menus, as well as information regarding alarms, the currently utilized configuration file name, and the valid time of the SCAN TVS

Table. The Menu/Information bar also contains the option buttons for Vert (to render the table vertically) and Tips (to provide helpful tips about table functions).

The File Menu

The File Menu options are for controlling the configuration files. The current configuration file is displayed on the menu button. This file indicates which configuration file (also known as the TVS Display Parameters file or TDP file) was last used in the meso table. The File Menu options are:

Retrieve Default TVS Configuration	Retrieves and uses the default configuration file.
Retrieve TVS Configuration...	Retrieves and uses a specified configuration file.
Save TVS Configuration	Saves only the TVS configuration file.
Save TVS Configuration As...	Saves the TVS configuration file to a new file, defined by the user.
Close TVS Table	Closes the TVS table until it is activated again from the SCAN Storm Cell Table.

The Configurations Menu

The Configurations Menu choices are for changing the alarm parameters and controlling the display of the TVS table. The Configurations Menu options are:

Alarm Time Setup. . .	Produces the Alarm Time Setup window. SCAN will issue a 'New' alarm if an event (cell, mesocyclone, or TVS) has been identified after a quiet period of no identifications. This window allows the user to define that quiet period in minutes.
Box Colors. . .	Produces the Attribute Color Threshold (ACT) window. The ACT window allows the user to define value ranges of each applicable TVS attribute. These value ranges are intended to reflect the degree of strength of the TVS, from white (weak) to yellow (moderate) to red (strong). These colors will be used when rendering the data on the D2D, in the table body, and in the time trends.

The Rank Menu

Allows the user to choose the TVS attribute by which the data in the table body will be sorted. The attribute that is currently being used for ranking will be displayed on this button. Refer to Appendix C to see which attributes can be used for ranking.

The Attributes Menu

Allows the user to choose which of the available TVS attributes will appear in the TVS table. Refer to Appendix C for information about all available attributes.

☐ Vert

Indicates whether or not the table is vertically rendered. If this button is activated, the table orientation will change from horizontal (default) to vertical.

☐ Tips

Indicates whether or not the Tips functionality is turned on. When this button is activated and the mouse cursor is focused over “clickable” widgets in the table, a pop-up box will appear next to the cursor containing useful information on the available features of that particular widget.

Valid Time

This displays the UTC time for which the data in the TVS table is valid.

The Attribute Title Row

Shows (in black) what attributes are currently selected for viewing. These represent the attributes selected from the Attributes menu described above.

Ranking By Attribute

Left-clicking on applicable attribute titles will sort the table data according to that attribute. Refer to Appendix C to see for which attributes the TVS table can be ranked.

Changing the Attribute Color Thresholds

Right-clicking on applicable attribute titles will bring up the Attribute Color Threshold (ACT) window, as described in the Configurations menu section above. Refer to Appendix C to see which attributes can be multi-colored in the TVS table.

The Table Body

Displays the TVS information, including such attributes as: storm cell ID, TVS ID, location (azm/range, lat/lon, state/county), and various physical characteristics of the TVS. If no TVSs have been identified, the message “NO TVS DETECTIONS” will appear in place of the table. The values for the various TVS attributes are displayed in the table body. Refer to Appendix C for a list of all TVS attributes available through SCAN.

Inspecting a TVS

Left-clicking on an identifier in the ‘ident’ column will cause the D2D to zoom-and-recenter on that particular TVS. This also fills the Inspection Row with data and highlights the identifier in the ‘ident’ column.

The Inspection Row

Duplicates the row in the table body for the TVS that was last inspected (see the “Table Body” section above for instructions on how to inspect a TVS). This row emphasizes the data for the identified TVS last inspected via the zoom-and-recenter method. The individual grid boxes in the Inspection Row have the same capabilities as the grid boxes in the table body, except left-clicking on the identifier box will zoom the D2D back out to the zoom level defined on the D2D menu bar. See Figure 1.

Zooming Back Out

Left-clicking on the identifier in the ‘ident’ column will cause the D2D to zoom back out.

SCAN TVS Table Sub-GUIs in Detail

New Alarm Time Setup Window

Same as for the cell table (see above).

Attribute Color Threshold (ACT) Window

Same as for the cell table (see above).

SCAN CWA Threat Index (SCTI)

Under the WarnGen button on the D2D, there is a button with the severe weather symbol. This is the Severe Weather SCTI button. The color of this button will reflect the general threat of severe weather over the County Warning Area (CWA).

- ☞ **White** indicates little or no activity in the CWA.
- ☞ **Green** indicates general thunderstorms with low severe weather probabilities in the CWA.
- ☞ **Yellow** indicates thunderstorms with moderate severe weather probabilities or a mesocyclone or TVS detected in the CWA.
- ☞ **Red** indicates thunderstorms with high severe weather probabilities and a mesocyclone and/or TVS detected in the CWA.
- ☞ **Grey** indicates the SCAN processor is not behaving properly or not running at all.

If the cursor is focused over this colored button, a small text tip widget will appear, providing the maximum value of the SCTI over the CWA and what it represents.

The actual grid of SCTI values over the CWA can be viewed as an image in the D2D, selectable from the SCAN menus. See the [SCAN homepage](http://www.nws.noaa.gov/mdl/scan) (<http://www.nws.noaa.gov/mdl/scan>) for more information regarding the SCTI.

SCAN “New” Alarms

A ‘new’ alarm will be issued if an event (cell, mesocyclone, or TVS) has been identified after a defined quiet period. In this case, WHETHER SCAN IS LOADED OR NOT, a window will appear in front of the D2D stating which type of event (cell, meso, TVS) has just been identified and suggesting SCAN be used to investigate. These new alarms can be turned off by editing the file /awips/fxa/data/evaluateNewAlarms.txt. 1 = on, 0 = off.

SCAN QPF

The SCAN processor also produces one-hour Quantitative Precipitation Forecasts (QPFs), based on algorithms developed by David Kitzmiller (former NWS-MDL). The algorithms use pattern recognition in conjunction with motion vectors and radar products to produce probabilities that a specified amount of precipitation will fall in one hour's time at a given location. The algorithms also forecast categorical amounts. Each can be displayed as a D2D graphic, selectable from the SCAN section of the radar menus on the D2D. See the [SCAN homepage](http://www.nws.noaa.gov/mdl/scan) (<http://www.nws.noaa.gov/mdl/scan>) for links to more information.

Data Monitoring System (DMS)

The SCAN Data Monitoring System (DMS) is a web browser-based, automated system for monitoring the status of the vital components of SCAN. It consists of a suite of HTML files, a Tcl/Tk Common Gateway Interface (CGI) script, and various supporting procedure, data, and image files. The system is housed on a web server, accessed through any browser that supports frames, and is updated using the CGI script. The following information is intended to give an overall description of the system display, defining the layout and components, and provide instructions for using the system.

DMS Display

See Figure 4.

The SCAN DMS display is divided into two frames. A small, static frame at the top of the page holds the title information and the button for updating the table information. The main frame below houses the data monitoring graphical elements.

For the SCAN processor to run optimally, AWIPS must receive the following products:

Name	Identifier	Product Number	Importance to the SCAN processor
Composite Reflectivity: 1 km	CZ	37	Vital!!
VIL	VIL	57	Vital
Base Reflectivity: 1 km	Z	19	Vital

Storm Track and Identification	STI	58	Suggested
Mesocyclone	M	60	Strongly Suggested
Tornado Vortex Signature	TVS	61	Strongly Suggested

Radar Products Information Table

The Radar Products Information table monitors the status of radar products for each dedicated radar (see the Glossary for a definition of the products). For each product, and for each dedicated radar, the monitor reports whether or not the product is on the Routine Products Set (RPS) list (Y for Yes, N for No), and gives the most recent data file's date and GMT time. If the product is absent from the RPS list, the background of the table cell containing the letter "N" will be colored red. If the product is not available, meaning there is no data file in the directory where it is stored, the monitor reports "None" and colors the background of the table cell red. Similarly, if a data file time is old, the background of the cell is colored red. A file is determined to be old according to a formula derived from the VCP mode (twice the length of the volume scan plus 2 minutes). If the VCP mode is not available, the default threshold value of 22 minutes is used. Directly under the radar identification letters (e.g., KLWX, KSHV, and KAKQ in Figure 4), there are two spaces per radar for reporting the current radar VCP mode, and the SCAN processor mode. The VCP mode is indicated with the pattern number (11, 21, 31, or 32). If the VCP space contains the phrase "VCP not available," it means the reported VCP number in the data file is not one of the four possible pattern numbers, or the data file containing the VCP number is old. The SCAN processor mode is indicated by either an icon of a radar (meaning SCAN is using radar information), or a lightning bolt (meaning SCAN is running only on lightning information). If the SCAN mode space contains the phrase "Mode not available," it means the data file containing the mode identifier is old and there is probably an urgent problem with the SCAN processor.

Note: The SCAN processor is triggered by the 1km Composite Reflectivity product. It is preferable for the QPF to have the STI product available, but it must have several current, consecutive volume scans of both VIL and Base Z.

CG Lightning Table

The top right table in the main frame is the CG Lightning Data table. This table monitors the status of the data file containing the latest cloud-to-ground lightning information. The most recent file date and time are given, along with the number of strikes since the top of the hour. The lightning data file is continuously updated, so the strike number may be different every time the page is loaded or updated. As with the previous table, a red background indicates an old file (in this case, older than 65 minutes). If the file is old, it either suggests a problem with the AWIPS acquisition of lightning data, or that there are no cloud-to-ground lightning strikes within

the National Lightning Detection Network in the Continental U.S.

Model Data Table

The bottom right table in the main frame is the Model Data table. This table monitors the status of the data file containing the latest model information that is used by the SCAN processor. The name of the model is given, along with the most recent data file date and time. As with the other tables, a red background indicates an old file. A file is determined to be old by a threshold that depends on the update interval of the model.

Remember, SCAN can still run without model data, but the *quality* of some of the derived attributes, such as percent chance of heavy precipitation, percent chance of severe weather, and (more indirectly) the severe weather SCAN CWA Threat Index (SCTI), may be slightly decreased.

The Probabilistic QPF (PQPF) algorithm also is enhanced by model data, but does not require it. The PQPF will use environmental winds to determine the motion vector of the reflectivity patterns. If the environmental data is not available, the algorithms will attempt to determine the motion vectors by pattern recognition from one radar image to another.

Using the DMS

Loading the DMS

Each time the web page is loaded in the browser window, the CGI script is run on the web server, and the information is sent to the screen. Thus, every time the “Reload” button is hit, the information will be updated. However, this is not the recommended method for updating the data. Reloading the entire page forces the browser to re-render information that does not need to be, and performance is diminished.

Updating the Information

In the static frame at the top of the display, there is a blue button labeled “UPDATE INFO.” Clicking this button will run the CGI script, retrieve the new information, and display it on the screen. Although they have the same end result, this method of updating the information is more efficient than hitting the “Reload” button on the browser toolbar.

Automatic Update Feature

For convenience, the DMS is equipped with an automatic update feature. This feature allows the user “hands-free” monitoring, updating the information automatically every two minutes. The user can also choose to update the information manually, using the “UPDATE INFO” button in the static frame at the top of the page.

Figures




Figure 1 This figure includes the D2D, SCAN Storm Cell Table, single trend, trend set, the Attribute Color Threshold, and Alarm Information windows.




Figure 2 The Storm Cell Identification Display (SCID) window.




Figure 3 This figure includes the D2D, SCAN Storm Cell Table, Configurations menu, Trend Set cascading menu, active trend set menu, Edit/Create Trend Set window, and a trend set example.




Figure 4 The SCAN Data Monitoring System display.




Figure 5 This is an example of the Mesocyclone Table and the vertical format of the Storm Cell table, with tip visible.

Help

To report problems or ask questions concerning the operation of SCAN in general, please use the SCAN list server (awips-scan@infolist.nws.noaa.gov). Please check the SCAN homepage at <http://www.nws.noaa.gov/mdl/scan> for more information, including the latest troubleshooting tips, version release information, and testing results.

Glossary

ACT - Attribute Color Threshold
CG - Cloud-to-ground
CGI - Common Gateway Interface
CWA - County Warning Area
CZ - Composite Reflectivity - 1km (a radar product)
D2D - Display 2 Dimensions
DMS - Data Monitoring System
GUI - Graphical User Interface
M - Mesocyclone (a radar product)
MDL - Meteorological Development Laboratory
RoCAT - Rate-of-change Alarm Threshold
RPS - Routine Products Set
RUC - Rapid Update Cycle
SCAN - System for Convection Analysis and Nowcasting
SCID - Storm Cell Identification Display
SCTI - SCAN CWA Threat Index
STI - Storm Tracking Information (a radar product)
TVS - Tornado Vortex Signature (a radar product)
VCP - Volume Coverage Pattern
VIL - Vertically Integrated Liquid (a radar product)
Z - Base Reflectivity - 1km (radar product)

Appendix A SCAN Storm Cell Table Attributes

Attribute	Definition	Units	Can be used for ranking?	Can be multi-colored?	Trend available?
ident	Storm Cell ID	Alphanumeric (A0-Z9)	Yes	No	No
azm	Current Azimuthal Position	Degrees	Yes	No	Yes
rng	Current Radial Position	nmi	Yes	No	Yes
rank	Storm Cell Rank	none	Yes	No	No
tvS	TVS Characteristics	Alphanumeric (NONE, TVS or ETVS)	No	Yes	No
meso	Mesocyclone Characteristics	Alphanumeric (NONE, UNCO, 3DCO, or MESO)	No	Yes	No
posh	Probability of Severe Hail	%	Yes	Yes	Yes
poh	Probability of Hail	%	Yes	Yes	Yes
hSize	Maximum Expected Hail Size	inches (diameter)	Yes	Yes	Yes
vil	Cell-Based VIL	kg/m ²	Yes	Yes	Yes
dbz	Maximum Reflectivity	dBZ	Yes	Yes	Yes
dbzHt	Height of Maximum Reflectivity	kft	Yes	No	Yes
top	Storm Top	kft	Yes	Yes	Yes
dir	Forecast Movement, Direction	Degrees	Yes	No	Yes
spd	Forecast Movement, Speed	kts	Yes	No	Yes

Attribute	Definition	Units	Can be used for ranking?	Can be multi-colored?	Trend available?
azm15	Forecast Azimuthal Position (15 min)	Degrees	No	No	No
rng15	Forecast Radial Position (15 min)	nmi	No	No	No
azm30	Forecast Azimuthal Position (30 min)	Degrees	No	No	No
rng30	Forecast Radial Position (30 min)	nmi	No	No	No
azm45	Forecast Azimuthal Position (45 min)	Degrees	No	No	No
rng45	Forecast Radial Position (45 min)	nmi	No	No	No
azm60	Forecast Azimuthal Position (60 min)	Degrees	No	No	No
rng60	Forecast Radial Position (60 min)	nmi	No	No	No
mvtErr	Forecast Movement Error, Error	nmi	No	No	No
mvtMn	Forecast Movement Error, Mean	nmi	No	No	No
lat	Latitude	Degrees	No	No	No
lon	Longitude	Degrees	No	No	No
polh	Probability of Large Hail	%	Yes	Yes	Yes
svrwx	Probability of Severe Weather	%	Yes	Yes	Yes
hvyPr	Probability of Heavy Precipitation	%	Yes	Yes	Yes
pPos	Percent Positive Lightning Strikes	%	Yes	Yes	Yes
cgRate	Cloud-to-Ground Lightning Rate	/min	Yes	Yes	Yes

Attribute	Definition	Units	Can be used for ranking?	Can be multi-colored?	Trend available?
vcp	Volume Coverage Pattern	none	No	No	No
cape	Storm CAPE	J/kg	Yes	Yes	Yes
sreh	Storm Relative Helicity	m ² /s ²	Yes	Yes	Yes
county	County Location	none	Yes	No	No

Appendix B SCAN Mesocyclone Table Attributes

Attribute	Definition	Units	Can be used for ranking?	Can be multi-colored?	Trend available?
strmID	Storm Cell ID	Alphanumeric (A0-Z9)	Yes	No	No
ident	Feature ID	Numeric (0-20)	Yes	No	No
type	Feature type	Alphanumeric (UNCO, 3DCO, MESO)	No	Yes	No
base	Base Value	kft	Yes	Yes	No
top	Top Value	kft	Yes	Yes	No
azm	Azimuthal Position	Degrees	Yes	No	No
rng	Radial Position	nmi	Yes	No	No
height	Height	kft	Yes	Yes	No
dRng	Diameter (Radial)	nmi	Yes	Yes	No
dAzm	Diameter (Azimuthal)	nmi	No	No	No
shear	Maximum Shear (tangential)	m/s/km (or E-3/sec)	Yes	Yes	No
lat	Latitude	Degrees	No	No	No
lon	Longitude	Degrees	No	No	No
county	County Location	none	Yes	No	No

Appendix C SCAN TVS Table Attributes

Attribute	Definition	Units	Used for ranking?	Multi-colored?	Trend available?
strmID	Storm Cell ID	Alphanumeric (A0-Z9)	Yes	No	No
ident	Feature ID	Numeric (01-25)	Yes	No	No
type	Feature type	Alphanumeric (TVS or ETVS)	No	Yes	No
azm	Azimuthal Position	Degrees	Yes	No	No
rng	Radial Position	nmi	Yes	No	No
avgDv	Average Delta Velocity	kts	Yes	Yes	No
lIDv	Low-level Delta Velocity	kts	Yes	Yes	No
maxDv	Maximum Delta Velocity	kts	Yes	Yes	No
mxDvHt	Maximum Delta Velocity Height	kft	Yes	Yes	No
base	Base Value	kft	Yes	Yes	No
depth	Depth Value	kft	Yes	Yes	No
top	Top Value	kft	Yes	Yes	No
shear	Maximum Shear	m/s/km (or E-3/sec)	Yes	Yes	No
shrHt	Height of the Maximum Shear	kft	Yes	Yes	No
lat	Latitude	Degrees	No	No	No
lon	Longitude	Degrees	No	No	No

Attribute	Definition	Units	Used for ranking?	Multi-colored?	Trend available?
county	County Location	none	Yes	No	No